

Topaz Workbench Fault Analytics Configuration Guide

Table Of Contents

Topaz Workbench Fault Analytics Configuration Guide	1
Getting Started	1
Related Topics	1
Configure the Compuware Fault Analytics Plug-In	1
Launching Fault Analytics.....	2
Index	3

Topaz Workbench Fault Analytics Configuration Guide

Getting Started

This help contains basic information needed to configure and launch Compuware Fault Analytics. Fault Analytics can be optionally installed into an Eclipse or RDz instance.

Related Topics

[Configure the Compuware Fault Analytics plug-In](#)

[Launch Fault Analytics](#)

Configure the Compuware Fault Analytics Plug-In

Specify the location of the Fault Analytics View Server to allow the installed Fault Analytics plug-in to connect.

To specify preferences for the Fault Analytics plug-in

1. Start the interface (Topaz Workbench or Eclipse) where the Fault Analytics plug-in is installed and select **Window > Preferences**. The Preferences dialog box appears.
2. Select **Compuware > Fault Analytics** (or, in Eclipse, select preference Fault Analytics). The Fault Analytics Web Interface - Server Definitions pane appears.
3. Click **Add**. The Fault Analytics: Add Server Definition dialog box appears.
4. In the **Host** and **Port** fields, enter the host name and port number of the system where Fault Analytics is installed.
5. In the **Description** field, enter a name for Fault Analytics. This becomes the option name from the **Compuware** menu that launches Fault Analytics.
6. Click **OK**. The server you defined appears in the **Fault Analytics Web Interface - Server Definitions** list on the Preferences dialog box.
7. Repeat steps 3 through 6 to specify additional server definitions, if desired.

To edit a server definition

1. Select the server definition in the **Fault Analytics Web Interface - Server Definitions** list and click **Edit**. The Fault Analytics: Edit Server Definition dialog box appears.
2. Make changes and click **OK**.

To remove server definitions

Do either of the following:

- To remove a single server definition, select the server definition in the **Fault Analytics Web Interface - Server Definitions** list and click **Remove**.
- To remove all server definitions in the list, click **Restore Defaults**.

To test a server connection

Select the server definition in the **Fault Analytics Web Interface - Server Definitions** list and click **Test**. A message indicates whether the connection was successful. If it was not, ensure that the data entered is correct and then contact the server administrator if necessary.

Launching Fault Analytics

To launch Fault Analytics

From the **Compuware** menu, select **Operations>Fault Analytics > *server_name***. Where *server_name* was the name specified during the [configuration of Fault Analytics](#). The Fault Analytics view launches in a Web browser. You can, optionally, detach the view by dragging it.

Related Topics

[Configure the Fault Analytics Plug-In](#)